

TASPRINT 464

The Style-Writer

**A
Tasman Software Program
for the
Amstrad CPC 464, 664, and 6128**

TASPRINT 464

© Copyright Tasman Software Ltd. 1984

The program is copyright and it is sold subject to the condition that it shall not be lent, resold, hired out, or otherwise circulated.

**Tasman Software Ltd
Springfield House
Hyde Terrace
Leeds LS2 9LN**

Reproduction or translation of any part of this work or the cassette computer program tapes that accompany this publication without permission of the copyright owner is unlawful.

1. INTRODUCTION

TASPRINT gives CPC 464 users with popular dot-matrix printers the option of printing in one of a set of five additional print styles. Each style of print is called a font.

TASPRINT produces output with characters that are twice the normal height of dot-matrix output. The width of each character may be greater or less than the normal width depending upon the graphics capabilities of the printer.

Each of the five TASPRINT fonts must be configured for the printer on which they are to be used. This is accomplished by loading and running the program on the TASPRINT tape as described in Section 2 below. The fonts are then saved onto a blank tape. To print using a TASPRINT font it is then only necessary to load the font from your tape before typing in or loading your own program.

2. LOADING AND CONFIGURING TASPRINT

Load and run TASPRINT by placing the cassette in the datacorder and typing:

RUN"

and pressing:

ENTER

Note that this can also be done by holding down the control [CTRL] key and pressing the small [ENTER] key on the numeric keypad. You will then be prompted to press the datacorder PLAY key and then any other key. The message:

Loading TASPRINT.BAS block 1

will appear on the screen as the program begins loading. Once the Basic program has loaded some explanatory text is shown on the screen while the five TASPRINT fonts are loaded. The complete loading process takes about seven minutes.

Once TASPRINT has loaded follow the instructions that appear on the screen to create the five fonts and machine code programs configured for your make of printer. You will then be prompted to save each of the fonts onto your own tape. The program stops after saving each font so that you may if you wish save each onto a separate tape. This facilitates finding and loading any required font.

3. LOADING A CONFIGURED TASPRINT FONT

Only one TASPRINT font may be loaded.

It is advisable to load a TASPRINT font immediately after the machine is turned on or reset and before loading any other program. It is essential to do this with programs such as AMSWORD/TASWORD 464 which assign all the available memory to their own use. A TASPRINT font will protect itself from these predatory programs.

To load a configured TASPRINT font put the tape containing the required font into the datacorder and execute one of the following:

```
RUN"LECTURA.BAS"  
RUN"MEDIAN.BAS"  
RUN"COMPACTA.BAS"  
RUN"DATARUN.BAS"  
RUN"PALACE.BAS"
```


To load the first font on the tape just execute:

RUN"

Once the font has loaded the "Ready" message will appear at the top of an empty screen. You can now type in your own commands or program or load a program from tape.

Once a font has loaded all characters sent to the printer by executing

PRINT#8 or LIST#8

will be intercepted by the TASPRINT software. The printer will print its normal character set until the font is turned on. The font is turned on by executing one of the first five of the following, depending on which font is loaded:

Font	Font on Command	Function Key
Lectura Light	PRINT#8,CHR\$(214)	1
Median	PRINT#8,CHR\$(215)	2
Compacta	PRINT#8,CHR\$(216)	3
Data Run	PRINT#8,CHR\$(217)	4
Palace Script	PRINT#8,CHR\$(218)	5
Any Font Off	PRINT#8,CHR\$(246)	9
Underline On	PRINT#8,CHR\$(212);	0
Underline Off	PRINT#8,CHR\$(244);	.

To facilitate the entry of the Font On commands TASPRINT automatically defines the appropriate function key when a font is loaded. For example, if Compacta is loaded then

PRINT#8,CHR\$(216) and [ENTER]

is obtained by holding down the [CTRL] key and pressing the [3] key on the numeric keypad.

Once the loaded font has been turned on using the appropriate Font On command all subsequent

PRINT#8 and LIST#8

statements will be printed in the TASPRINT font. To turn the font off and revert to normal printing use the function key [CTRL] [9] to obtain:

PRINT#8,CHR\$(246) and [ENTER]

as indicated in the above table of TASPRINT commands.

While the font is turned on output may be underlined by [CTRL] [0], or equivalently, by

PRINT#8,CHR\$(212);

Underlining is turned off by [CTRL] [.] which is equivalent to:

PRINT#8,CHR\$(244);

4. THE TASPRTINT CHARACTER SET

The TASPRTINT character set consists of the standard ASCII symbols and the 2nd character set used by AMSWORD/TASWORD 464. This character set is listed in the appendix.

For example, to print the â character: This character is listed in the appendix as having code 164. To print this character when a TASPRTINT font is On execute:

PRINT #8,CHR\$(164)

5. TASPRTINT AND AMSWORD/TASWORD 464

5.1 CONFIGURING AMSWORD/TASWORD 464

THIS SECTION ONLY APPLIES TO VERSION 1.02 OF AMSWORD/TASWORD 464. NO CONFIGURING IS NECESSARY FOR SUBSEQUENT VERSIONS. TO SEE YOUR VERSION NUMBER GO INTO BASIC AND EXECUTE LIST 10.

- (1) Load AMSWORD/TASWORD in the usual way (RUN");
- (2) Go into Basic by pressing [CTRL] [ENTER] and then [B] followed by [ENTER];
- (3) Place the TASPRTINT tape in the datacorder;
- (4) Type: MERGE "TP" and press [ENTER];
- (5) You will be prompted to press the PLAY button and then any key. This merges a short program which is recorded on the TASPRTINT tape immediately after the fonts;
- (6) Type RUN and press [ENTER] and after the "Ready" prompt appears type RUN and press [ENTER] again;
- (7) You will see the word processing program running normally. Save your modified program as described on page 9 of the program manual.

5.2 LOADING TASPRTINT AND AMSWORD/TASWORD 464

Load the required font first as described in Section 3. Then load your AMSWORD or TASWORD 464 in the normal way by executing RUN".

AMSWORD/TASWORD will run normally once loaded. If you access the main menu by [CTRL] [ENTER] then you will see that the characters free count is reduced by about 5,000 characters. This is because the font is occupying memory space which is otherwise free for the text file.

5.3 USING TASPRINT WITH AMSWORD/TASWORD 464

AMSWORD and TASWORD 464 reclaim the function keys for their own use as described on page 45 of the program manual. The TASPRINT font that is loaded is turned On by typing the appropriate printer control character into the text. These printer control characters are the inverse capital letters V through to Z as shown in the bottom right hand corner of the help page. Each of these inverse characters will print as a space and will turn the font On for TASPRINT printing beginning with the start of the line containing the control character.

The printer control characters given by the lower case inverse letters v through z turn the font Off and normal printing commences from the beginning of the line containing the control character.

The printer control character inverse T will turn TASPRINT underlining on and inverse t turns underlining off.

AMSWORD/TASWORD sends the codes associated with the normal and second character set characters as described on pages 34, 37 and 39 of the program manuals. If a character is redefined to be, for example, printed as a character followed by a backspace followed by another overprinted character, then when the TASPRINT font is turned on it will be printed as three separate TASPRINT characters.

Printer control characters other than the TASPRINT printer control characters should not be embedded in text that is to be printed with the TASPRINT font turned on.

The number of TASPRINT characters that a printer can print on one line varies according to the make of printer. The TASPRINT configuring program specifies this line length for your make of printer when run. Lines of text that exceed this line length will wrap round onto the next line, and word-wrap and justification will be lost. If you are using a printer that prints, for example, 48 TASPRINT characters per line then it is advisable to set the right margin at column 48 before typing text that is to be printed with the TASPRINT font turned on.

6. USING TASPRINT WITH OTHER PROGRAMS

TASPRINT can be used with other programs provided that after loading a TASPRINT font there is enough free memory remaining for the other program to load and run and provided that the other program does not reset the Machine Pack indirection MC PRINT CHAR at #BD2B. For these reasons the successful use of TASPRINT with other commercially available programs cannot be guaranteed.

APPENDIX - CHARACTERS AND CODES

14	15	16	17	18	19	20	21	22	23	24
■	▼	△	←	↓	↑	→	■	■	✕	♣
25	26	27	28	29	30	31	32	33	34	35
■	Æ	à	³	³	²	²		!	"	#
36	37	38	39	40	41	42	43	44	45	46
\$	%	&	,	()	*	+	,	-	.
47	48	49	50	51	52	53	54	55	56	57
/	Ø	1	2	3	4	5	6	7	8	9
58	59	60	61	62	63	64	65	66	67	68
:	;	<	=	>	?	@	A	B	C	D
69	70	71	72	73	74	75	76	77	78	79
E	F	G	H	I	J	K	L	M	N	O
80	81	82	83	84	85	86	87	88	89	90
P	Q	R	S	T	U	V	W	X	Y	Z
91	92	93	94	95	96	97	98	99	100	101
[\]	↑	-	`	a	b	c	d	e
102	103	104	105	106	107	108	109	110	111	112
f	g	h	i	j	k	l	m	n	o	p
113	114	115	116	117	118	119	120	121	122	123
q	r	s	t	u	v	w	x	y	z	{
124	125	126	127	128	129	130	131	132	133	134
!	}	~	£	½	¼	¾	⅓	⅔	■	Ø
135	136	137	138	139	140	141	142	143	144	145
ø	æ	@	œ	¿	À	Á	Ò	Ψ	Δ	ê
146	147	148	149	150	151	152	153	154	155	156
Θ	Γ	Ü	ï	î	í	Λ	ñ	ñ	Φ	Π
157	158	159	160	161	162	163	164	165	166	167
̄	É	Σ	ë	ü	ö	Ω	â	Ö	Å	ô
168	169	170	171	172	173	174	175	176	177	178
ç	û	Þ	ß	β	α	β	ψ	δ	€	Θ
179	180	181	182	183	184	185	186	187	188	189
ø	η	ι	ì	κ	λ	μ	ν	Φ	π	ξ
190	191	192								
ƒ	σ	τ								
219	220	221	222	223	224					
u	ä	ω	Χ	ς	ς					
251	252	253								
é	à	è								

TASPRINT 464

The Style-Writer

Tasprint 464 drives the following printers

Amstrad DMP 1
Epson FX-80
Epson RX-80
Epson MX-80 Type III
Shinwa CP-80
Mannesmann Tally MT80
Star DMP 510/515
Brother HR5